Modern C++ Programming

3. Basic Concepts II

INTEGRAL AND FLOATING-POINT TYPES

Federico Busato

Table of Context

Integral Data Types

- Fixed Width Integers
- size_t and ptrdiff_t
- When Use Signed/Unsigned Integer?
- Promotion, Truncation
- Undefined Behavior

Table of Context

Floating-point Types and Arithmetic

- IEEE Floating-point Standard and Other Representations
- Normal/Denormal Values
- Infinity
- Not a Number (NaN)
- Machine Epsilon
- Units at the Last Place (ULP)
- Cheatsheet
- Summary
- Arithmetic Properties
- Detect Floating-point Errors ★

Table of Context

3 Floating-point Issues

- Catastrophic Cancellation
- Floating-point Comparison

Integral Data Types

A Firmware Bug

"Certain SSDs have a firmware bug causing them to irrecoverably fail after exactly 32,768 hours of operation. SSDs that were put into service at the same time will fail simultaneously, so RAID won't help"

HPE SAS Solid State Drives - Critical Firmware Upgrade



Overflow Implementations



The latest news from Google AI

Extra, Extra - Read All About It: Nearly All Binary Searches and Mergesorts are Broken

Friday, June 2, 2006

Posted by Joshua Bloch, Software Engineer

Note: Computing the average in the right way is not trivial, see On finding the average of two unsigned integers without overflow

related operations: ceiling division, rounding division

Potentially Catastrophic Failure



 $51 \ days = 51 \cdot 24 \cdot 60 \cdot 60 \cdot 1000 = 4406400000 \ ms$

Boeing 787s must be turned off and on every 51 days to prevent 'misleading data' being shown to pilots

C++ Data Model

LP32 Windows 16-bit APIs (no more used)

ILP32 Windows 32-bit APIs, Unix 32-bit (Linux, Mac OS)

LLP64 Windows 64-bit APIs

LP64 Linux 64-bit APIs

Model/Bits	short	int	long	long long	pointer
ILP32	16	32	32	64	32
LLP64	16	32	32	64	64
LP64	16	32	64	64	64

char is always 1 byte

int*_t <cstdint>

C++ provides fixed width integer types.

They have the same size on any architecture:

int8_t, uint8_t
int16_t, uint16_t
int32_t, uint32_t
int64_t, uint64_t

Good practice: Prefer fixed-width integers instead of native types. int and unsigned can be directly used as they are widely accepted by C++ data models

int*_t types are not "real" types, they are merely typedefs to appropriate
fundamental types

C++ standard does not ensure a one-to-one mapping:

- There are five distinct fundamental types (char, short, int, long, long long)
- There are four int*_t overloads (int8_t, int16_t, int32_t, and int64_t)

ithare.com/c-on-using-int_t-as-overload-and-template-parameters

 $\underline{\text{Warning}}$: I/O Stream interprets uint8_t and int8_t as char and not as integer values

```
int8_t var;
cin >> var; // read '2'
cout << var; // print '2'
int a = var * 2;
cout << a; // print '100' !!</pre>
```

size_t and ptrdiff_t

size_t ptrdiff_t <cstddef>

size_t and ptrdiff_t are aliases data types capable of storing the biggest
representable value on the current architecture

- size_t is an <u>unsigned integer</u> type (of at least 16-bit)
- ptrdiff_t is the signed version of size_t commonly used for computing pointer differences
- size_t is commonly used to represent size measures
- size_t / ptrdiff_t are 4 bytes on 32-bit architectures, and 8 bytes on 64-bit architectures
- C++23 adds uz / UZ literal for size_t
- C++23 adds z / Z literal for ptrdiff_t

Signed and unsigned integers use the same hardware for their operations, but they have very <u>different semantic</u>:

signed integers

- lacksquare Represent positive, negative, and zero values (\mathbb{Z})
- More negative values $(2^{31} 1)$ than positive $(2^{31} 2)$
- Overflow/underflow is <u>undefined behavior</u>

Possible behavior:

- overflow: $(2^{31} 1) + 1 \rightarrow min$ underflow: $-2^{31} - 1 \rightarrow max$
- Bit-wise operations are implementation-defined
- Commutative, reflexive, not associative (overflow/underflow)

unsigned integers

- Represent only *non-negative* values (\mathbb{N})
- Overflow/underflow is well-defined (modulo 2³²)
- Discontinuity in 0, $2^{32} 1$
- Bit-wise operations are <u>well-defined</u>
- Commutative, reflexive, associative

When Use Signed/Unsigned Integer?

Google Style Guide

Because of historical accident, the C++ standard also uses unsigned integers to represent the size of containers - many members of the standards body believe this to be a mistake, but it is effectively impossible to fix at this point

```
Solution: use int64_t
```

```
max value: 2^{63}-1=9,223,372,036,854,775,807 or 9 quintillion (9 billion of billion), about 292 years (nanoseconds), 9 million terabytes
```

Arithmetic Type Limits

Query properties of arithmetic types in C++11:

* this syntax will be explained in the next lectures

Promotion and Truncation

Promotion to a larger type keeps the sign

```
int16_t x = -1;
int     y = x; // sign extend
cout << y;     // print -1</pre>
```

Truncation to a smaller type is implemented as a modulo operation with respect to the number of bits of the smaller type

```
unsigned a = 10;  // array is small
int    b = -1;
array[10ull + a * b] = 0; // ?

Segmentation fault!

int f(int a, unsigned b, int* array) { // array is small
    if (a > b)
        return array[a - b]; // ?
```

```
Segmentation fault for a < 0!</p>
```

return 0;

```
// v.size() return unsigned
for (size_t i = 0; i < v.size() - 1; i++)
    array[i] = 3; // ?</pre>
```

Segmentation fault for v.size() == 0!

Easy case:

What about the following code?

19/66

More negative values than positive

A pratical example:

Initialize an integer with a value larger then its range is undefined behavior

```
int z = 3000000000; // undefined behavior!!
```

Bitwise operations on signed integer types is undefined behavior

```
int y = 1 << 12;  // undefined behavior!!</pre>
```

Shift larger than #bits of the data type is undefined behavior even for unsigned

```
unsigned y = 1u << 32u; // undefined behavior!!</pre>
```

Undefined behavior in implicit conversion

```
uint16_t a = 65535; // OxFFFF
uint16_t b = 65535; // OxFFFF
cout << (a * b); // print '-131071' undefined behavior!! (int overflow)</pre>
```

Even worse example:

```
#include <iostream>
int main() {
    for (int i = 0; i < 4; ++i)
        std::cout << i * 1000000000 << std::endl:
// with optimizations, it is an infinite loop
// --> 1000000000 * i > INT MAX
// undefined behavior!!
// the compiler translates the multiplication constant into an addition
```

Is the following loop safe?

- What happens if size is equal to INT_MAX?
- How to make the previous loop safe?
- i >= 0 && i < size is not the solution because of undefined behavior of signed overflow
- Can we generalize the solution when the increment is i += step?

Overflow / Underflow

Detecting overflow/underflow for unsigned integral types is **not trivial**

```
// some examples
bool is_add_overflow(unsigned a, unsigned b) {
   return (a + b) < a || (a + b) < b;
}
bool is_mul_overflow(unsigned a, unsigned b) {
   unsigned x = a * b;
   return a != 0 && (x / a) != b;
}</pre>
```

Overflow/underflow for <u>signed integral</u> types is **not defined** !! *Undefined behavior* must be checked before performing the operation

Floating-point Types

and Arithmetic

IEEE Floating-Point Standard

IEEE754 is the technical standard for floating-point arithmetic

The standard defines the binary format, operations behavior, rounding rules, exception handling, etc.

- First Release: 1985
- Second Release: 2008. Add 16-bit floating point
- Third Release: 2019. Specify min/max behavior

see The IEEE Standard 754: One for the History Books

IEEE764 technical document:

754-2019 - IEEE Standard for Floating-Point Arithmetic

In general, C/C++ adopts IEEE754 floating-point standard:

en.cppreference.com/w/cpp/types/numeric_limits/is_iec559

32/64-bit Floating-Point

• IEEE764 Single precision (32-bit) float

Sign 1-bit Exponent (or base)
8-bit

Mantissa (or significant) 23-bit

■ IEEE764 Double precision (64-bit) double

Sign

1-bit

Exponent (or base)

11-bit

Mantissa (or significant)
52-bit

16-bit Floating-Point

Standardized in C++23

■ IEEE754 16-bit Floating-point (std::binary16) → GPU, Arm7

Sign Exponent Mantissa
1-bit 5-bit 10-bit

ullet Google 16-bit Floating-point (std::bfloat16) ightarrow TPU, GPU, Arm8

Sign Exponent Mantissa
1-bit 8-bit 7-bit

8-bit Floating-Point (Non-Standardized in C++/IEEE)

■ E4M3



■ E5M2



- Floating Point Formats for Machine Learning, *IEEE draft*
- FP8 Formats for Deep Learning, Intel, Nvidia, Arm

Other Real Value Representations (Non-standardized in C++/IEEE)

- TensorFloat-32 (TF32) Specialized floating-point format for deep learning applications
- Posit (John Gustafson, 2017), also called unum III (universal number), represents floating-point values with variable-width of exponent and mantissa.
 It is implemented in experimental platforms

- NVIDIA Hopper Architecture In-Depth
- Beating Floating Point at its Own Game: Posit Arithmetic
- Posits, a New Kind of Number, Improves the Math of AI
- Comparing posit and IEEE-754 hardware cost

 Microscaling Formats (MX) Specification for low-precision floating-point formats defined by AMD, Arm, Intel, Meta, Microsoft, NVIDIA, and Qualcomm. It includes FP8, FP6, FP4, (MX)INT8

• **Fixed-point** representation has a fixed number of digits after the radix point (decimal point). The gaps between adjacent numbers are always equal. The range of their values is significantly limited compared to floating-point numbers. It is widely used on embedded systems

Floating-point number:

- Radix (or base): β
- Precision (or digits): p
- Exponent (magnitude): e
- Mantissa: M

$$n = \underbrace{M}_{p} \times \beta^{e} \rightarrow IEEE754: 1.M \times 2^{e}$$

```
float f1 = 1.3f; // 1.3

float f2 = 1.1e2f; // 1.1 · 10^2

float f3 = 3.7E4f; // 3.7 · 10^4

float f4 = .3f; // 0.3

double d1 = 1.3; // without "f"

double d2 = 5E3; // 5 · 10^3
```

Exponent Bias

In IEEE754 floating point numbers, the exponent value is offset from the actual value by the **exponent bias**

- The exponent is stored as an unsigned value suitable for comparison
- Floating point values are <u>lexicographic ordered</u>
- For a single-precision number, the exponent is stored in the range [1,254] (0 and 255 have special meanings), and is <u>biased</u> by subtracting 127 to get an exponent value in the range [-126, +127]

0 10000111
+
$$2^{(135-127)} = 2^8$$

$$\begin{array}{c} 1100000000000000000000000\\ \frac{1}{2^1} + \frac{1}{2^2} = 0.5 + 0.25 = 0.75 \stackrel{\textit{normal}}{\rightarrow} 1.75 \end{array}$$

$$+1.75*2^8 = 448.0$$

Normal number

A **normal** number is a floating point value that can be represented with *at least one* bit set in the exponent or the mantissa has all 0s


Denormal number

Denormal (or subnormal) numbers fill the underflow gap around zero in floating-point arithmetic. Any non-zero number with magnitude smaller than the smallest normal number is denormal

A **denormal** number is a floating point value that can be represented with *all 0s in the exponent*, but the mantissa is non-zero


Why denormal numbers make sense:

(↓ normal numbers)



The problem: distance values from zero

(↓ denormal numbers)



Infinity

In the IEEE754 standard, inf (infinity value) is a numeric data type value that exceeds the maximum (or minimum) representable value

Operations generating inf:

- $\pm \infty \cdot \pm \infty$
- $\pm \infty \cdot \pm$ finite_value
- finite_value op finite_value > max_value
- non-NaN $/\pm 0$

There is a single representation for +inf and -inf

Comparison: (inf == finite_value)
$$\rightarrow$$
 false $(\pm \inf$ == $\pm \inf$) \rightarrow true

```
cout << 0 / 0;  // undefined behavior</pre>
cout << 0.0 / 0.0; // print "nan"
cout << 5.0 / 0.0; // print "inf"
cout << -5.0 / 0.0; // print "-inf"</pre>
auto inf = std::numeric_limits<float>::infinity;
cout << (-0.0 == 0.0);
                                         // true. 0 == 0
cout << ((5.0f / inf) == ((-5.0f / inf)); // true, 0 == 0
cout << (10e40f) == (10e40f + 9999999.0f); // true, inf == inf
cout << (10e40) == (10e40f + 9999999.0f); // false, 10e40 != inf
```

Not a Number (NaN)

NaN

In the IEEE754 standard, NaN (not a number) is a numeric data type value representing an undefined or unrepresentable value

Operations generating NaN:

- Operations with a NaN as at least one operand
- \bullet $\pm\infty\cdot\mp\infty$, $0\cdot\infty$
- $0/0, \infty/\infty$
- \sqrt{x} , $\log(x)$ for x < 0
- $\sin^{-1}(x), \cos^{-1}(x)$ for x < -1 or x > 1

There are many representations for NaN (e.g. $2^{24}-2$ for float)

Comparison: (NaN == x)
$$\rightarrow$$
 false, for every x (NaN == NaN) \rightarrow false

Machine Epsilon

Machine epsilon

Machine epsilon ε (or *machine accuracy*) is defined to be the smallest number that can be added to 1.0 to give a number other than one

IEEE 754 Single precision : $\varepsilon = 2^{-23} \approx 1.19209*10^{-7}$

IEEE 754 Double precision : $\varepsilon = 2^{-52} \approx 2.22045*10^{-16}$

Units at the Last Place (ULP)

ULP

Units at the Last Place is the gap between consecutive floating-point numbers

$$ULP(p, e) = \beta^{e-(p-1)} \to 2^{e-(p-1)}$$

Example:

$$\beta = 10, \ p = 3$$

 $\pi = 3.1415926... \rightarrow x = 3.14 \times 10^{0}$
 $ULP(3,0) = 10^{-2} = 0.01$

Relation with ε :

- $\varepsilon = ULP(p,0)$
- $ULP_x = \varepsilon * \beta^{e(x)}$

Floating-Point Representation of a Real Number

The machine <u>floating-point representation</u> **fl(**x**)** of a *real number* x is expressed as $fl(x) = x(1 + \delta)$, where δ is a small constant

The approximation of a *real number* x has the following properties:

Absolute Error:
$$|fl(x) - x| \le \frac{1}{2} \cdot ULP_x$$

Relative Error:
$$\left| \frac{fl(x) - x}{x} \right| \leq \frac{1}{2} \cdot \varepsilon$$

Floating-point - Cheatsheet

• NaN (mantissa \neq 0)

• ± infinity

- 11111111

11111111111111111111111111

- 11111111
 - Lowest/Largest ($\pm 3.40282 * 10^{+38}$) 11111110
 - Minimum (normal) ($\pm 1.17549 * 10^{-38}$) 00000001
- Denormal number ($< 2^{-126}$)(minimum: $1.4 * 10^{-45}$)
 - 00000000

+0

- 00000000

	E4M3	E5M2	half
Exponent	4 [0*-14] (no inf)	5-bit [0*-30]	
Bias	7	15	
Mantissa	4-bit	2-bit	10-bit
Largest (\pm)	1.75 * 2 ⁸ 448	$1.75 * 2^{15}$ $57,344$	2 ¹⁶ 65,536
Smallest (\pm)	2^{-6} 0.015625	2^{-14} 0.00006	
Smallest (denormal*)	2^{-9} 0.001953125	2^{-16} $1.5258 * 10^{-5}$	$2^{-24} \\ 6.0 \cdot 10^{-8}$
Epsilon	2 ⁻⁴ 0.0625	2^{-2} 0.25	2^{-10} 0.00098

	bfloat16	float	double
Exponent	8-bit [0*-254]		11-bit [0*-2046]
Bias	127		1023
Mantissa	7-bit	23-bit	52-bit
$Largest\ (\pm)$	$2^{128} \\ 3.4 \cdot 10^{38}$		$2^{1024} \\ 1.8 \cdot 10^{308}$
Smallest (\pm)	2^{-126} $1.2 \cdot 10^{-38}$		2^{-1022} $2.2 \cdot 10^{-308}$
Smallest (denormal*)	/	2^{-149} $1.4 \cdot 10^{-45}$	2^{-1074} $4.9 \cdot 10^{-324}$
Epsilon	2^{-7} 0.0078	$2^{-23} \\ 1.2 \cdot 10^{-7}$	$2^{-52} \\ 2.2 \cdot 10^{-16}$

Floating-point - Limits

```
#include <liimits>
// T: float or double
std::numeric limits<T>::max(); // largest value
std::numeric_limits<T>::lowest();  // lowest value (C++11)
std::numeric limits<T>::min(): // smallest value
std::numeric_limits<T>::denorm_min() // smallest (denormal) value
std::numeric_limits<T>::epsilon(); // epsilon value
std::numeric limits<T>::infinity() // infinity
std::numeric_limits<T>::quiet_NaN() // NaN
```

Floating-point - Useful Functions

```
#include <cmath> // C++11
bool std::isnan(T value) // check if value is NaN
bool std::isinf(T value) // check if value is \pm infinity
bool std::isfinite(T value) // check if value is not NaN
                            // and not \pm infinity
bool std::isnormal(T value): // check if value is Normal
    std::ldexp(T x, p) // exponent shift x * 2^p
Τ
    std::ilogb(T value) // extracts the exponent of value
int
```

Floating-point operations are written

- ⊕ addition
- ⊖ subtraction
- ⊗ multiplication
- ⊘ division

$$\odot \in \{\oplus,\ominus,\otimes,\oslash\}$$

 $op \in \{+, -, *, \setminus\}$ denotes exact precision operations

- (P1) In general, a op $b \neq a \odot b$
 - (P2) Not Reflexive $a \neq a$
 - Reflexive without NaN
- (P3) Not Commutative $a \odot b \neq b \odot a$
 - Commutative without NaN (NaN ≠ NaN)
 - (P4) In general, Not Associative $(a \odot b) \odot c \neq a \odot (b \odot c)$
 - (P5) In general, **Not Distributive** $(a \oplus b) \otimes c \neq (a \cdot c) \oplus (b \cdot c)$
- (P6) Identity on operations is not ensured $(k \oslash a) \otimes a \neq k$
- (P7) No overflow/underflow Floating-point has "saturation" values inf, -inf
 - Adding (or subtracting) can "saturate" before inf, -inf

C++11 allows determining if a floating-point exceptional condition has occurred by using floating-point exception facilities provided in <cfenv>

```
#include <cfenv>
// MACRO
FE DIVBYZERO // division by zero
FE_INEXACT // rounding error
FE_INVALID // invalid operation, i.e. NaN
FE_OVERFLOW // overflow (reach saturation value +inf)
FE_UNDERFLOW // underflow (reach saturation value -inf)
FE ALL EXCEPT // all exceptions
// functions
std::feclearexcept(FE ALL EXCEPT); // clear exception status
std::fetestexcept(<macro>);  // returns a value != 0 if an
                                  // exception has been detected
```

Detect Floating-point Errors *

```
#include <cfenv> // floating point exceptions
#include <iostream>
#pragma STDC FENV ACCESS ON // tell the compiler to manipulate the floating-point
                          // environment (not supported by all compilers)
                          // qcc: yes, clanq: no
int main() {
   std::feclearexcept(FE_ALL_EXCEPT); // clear
   auto x = 1.0 / 0.0; // all compilers
   std::cout << (bool) std::fetestexcept(FE_DIVBYZERO); // print true
   std::feclearexcept(FE_ALL_EXCEPT); // clear
   auto x2 = 0.0 / 0.0; // all compilers
   std::cout << (bool) std::fetestexcept(FE_INVALID); // print true
   std::feclearexcept(FE_ALL_EXCEPT); // clear
   auto x4 = 1e38f * 10; // acc: ok
   std::cout << std::fetestexcept(FE OVERFLOW); // print true</pre>
```

Floating-point Issues



Ariene 5: data conversion from 64-bit floating point value to 16-bit signed integer \rightarrow \$137 million



Patriot Missile: small chopping error at each operation, 100 hours activity \rightarrow 28 deaths

Integer type is more accurate than floating type for large numbers

float numbers are different from double numbers

```
cout << (1.1 != 1.1f); // print true !!!
```

The floating point precision is finite!

Floating point arithmetic is not associative

```
cout << 0.1 + (0.2 + 0.3) == (0.1 + 0.2) + 0.3; // print false
```

IEEE764 Floating-point computation guarantees to produce **deterministic** output, namely the exact bitwise value for each run, <u>if and only if</u> the **order of the operations** is always the same

ightarrow same result on any machine and for all runs

54/66

"Using a double-precision floating-point value, we can represent easily the number of atoms in the universe.

If your software ever produces a number so large that it will not fit in a double-precision floating-point value, chances are good that you have a bug"

Daniel Lemire, Prof. at the University of Quebec

"NASA uses just 15 digits of π to calculate interplanetary travel. With 40 digits, you could calculate the circumference of a circle the size of the visible universe with an accuracy that would fall by less than the diameter of a single hydrogen atom"

Latest in space, Twitter

Floating-point Algorithms


- addition algorithm (simplified):
- (1) Compare the exponents of the two numbers. Shift the smaller number to the right until its exponent would match the larger exponent
- (2) Add the mantissa
- (3) Normalize the sum if needed (shift right/left the exponent by 1)
- multiplication algorithm (simplified):
- (1) Multiplication of mantissas. The number of bits of the result is twice the size of the operands (46+2 bits, with +2 for implicit normalization)
- (2) Normalize the product if needed (shift right/left the exponent by 1)
- (3) Addition of the exponents
- fused multiply-add (fma):
 - Recent architectures (also GPUs) provide fma to compute addition and multiplication in a single instruction (performed by the compiler in most cases)
 - The rounding error of fma(x, y, z) is less than $(x \otimes y) \oplus z$

Catastrophic Cancellation

Catastrophic cancellation (or *loss of significance*) refers to loss of relevant information in a floating-point computation that cannot be revered

Two cases:

- (C1) $\mathbf{a} \pm \mathbf{b}$, where $\mathbf{a} \gg \mathbf{b}$ or $\mathbf{b} \gg \mathbf{a}$. The value (or part of the value) of the smaller number is lost
- (C2) $\mathbf{a} \mathbf{b}$, where \mathbf{a}, \mathbf{b} are approximation of exact values and $\mathbf{a} \approx \mathbf{b}$, namely a loss of precision in both \mathbf{a} and \mathbf{b} . $\mathbf{a} \mathbf{b}$ cancels most of the relevant part of the result because $\mathbf{a} \approx \mathbf{b}$. It implies a *small absolute error* but a *large relative error*



How many iterations performs the following code?

```
while (x > 0)

x = x - y;
```

How many iterations?

```
float: x = 10,000,000 y = 1 -> 10,000,000

float: x = 30,000,000 y = 1 -> does not terminate

float: x = 200,000 y = 0.001 -> does not terminate

bfloat: x = 256 y = 1 -> does not terminate !!
```

Floating-point increment

```
float x = 0.0f;
for (int i = 0; i < 20000000; i++)
x += 1.0f;</pre>
```

What is the value of x at the end of the loop?

Ceiling division $\left\lceil \frac{a}{b} \right\rceil$

```
// std::ceil((float) 101 / 2.0f) -> 50.5f -> 51
float x = std::ceil((float) 20000001 / 2.0f);
```

What is the value of x?

Let's solve a quadratic equation:

$$x_{1,2} = \frac{-b \pm \sqrt{b^2 - 4ac}}{2a}$$

```
x² + 5000x + 0.25

(-5000 + std::sqrt(5000.0f * 5000.0f - 4.0f * 1.0f * 0.25f)) / 2 // x2

(-5000 + std::sqrt(25000000.0f - 1.0f)) / 2 // catastrophic cancellation (C1)
(-5000 + std::sqrt(25000000.0f)) / 2

(-5000 + 5000) / 2 = 0 // catastrophic cancellation (C2)
// correct result: 0.00005!!
```

relative error:
$$\frac{|0 - 0.00005|}{0.00005} = 100\%$$

The problem

```
cout << (0.11f + 0.11f < 0.22f); // print true!!
cout << (0.1f + 0.1f > 0.2f); // print true!!
```

Do not use absolute error margins!!

```
bool areFloatNearlyEqual(float a, float b) {
   if (std::abs(a - b) < epsilon); // epsilon is fixed by the user
      return true;
   return false;
}</pre>
```

Problems:

- Fixed epsilon "looks small" but it could be too large when the numbers being compared are very small
- If the compared numbers are very large, the epsilon could end up being smaller than the smallest rounding error, so that the comparison always returns false

Solution: Use relative error $\frac{|a-b|}{b} < \varepsilon$

```
bool areFloatNearlyEqual(float a, float b) {
   if (std::abs(a - b) / b < epsilon); // epsilon is fixed
      return true;
   return false;
}</pre>
```

Problems:

- a=0, b=0 The division is evaluated as 0.0/0.0 and the whole if statement is (nan < espilon) which always returns false
- b=0 The division is evaluated as abs(a)/0.0 and the whole if statement is (+inf < espilon) which always returns false
- a and b very small. The result should be true but the division by b may produces wrong results
- It is not commutative. We always divide by b

```
Possible solution: \frac{|a-b|}{\max(|a|,|b|)} < \varepsilon
```

```
bool areFloatNearlyEqual(float a, float b) {
    constexpr float normal min = std::numeric limits<float>::min();
    constexpr float relative error = <user defined>
    if (!std::isfinite(a) || !isfinite(b)) // a = \pm \infty, NaN or b = \pm \infty, NaN
        return false:
    float diff = std::abs(a - b):
    // if "a" and "b" are near to zero, the relative error is less effective
    if (diff <= normal_min) // or also: user_epsilon * normal_min</pre>
        return true:
    float abs_a = std::abs(a);
    float abs_b = std::abs(b);
    return (diff / std::max(abs_a, abs_b)) <= relative_error;</pre>
```

Minimize Error Propagation - Summary

- Prefer multiplication/division rather than addition/subtraction
- Try to reorganize the computation to keep near numbers with the same scale (e.g. sorting numbers)
- Consider to put a zero very small number (under a threshold). Common application: iterative algorithms
- Scale by a power of two is safe
- Switch to log scale. Multiplication becomes Add, and Division becomes Subtraction
- Use a compensation algorithm like Kahan summation, Dekker's FastTwoSum, Rump's AccSum

References

Suggest readings:

- What Every Computer Scientist Should Know About Floating-Point Arithmetic
- Do Developers Understand IEEE Floating Point?
- Yet another floating point tutorial
- Unavoidable Errors in Computing


Floating-point Comparison readings:

- The Floating-Point Guide Comparison
- Comparing Floating Point Numbers, 2012 Edition
- Some comments on approximately equal FP comparisons
- Comparing Floating-Point Numbers Is Tricky

Floating point tools:

- IEEE754 visualization/converter
- Find and fix floating-point problems

On Floating-Point



DURING A COMPETITION, I TOLD THE PROGRAMMERS ON OUR TEAM THAT e^{π} - π WAS A STANDARD TEST OF FLOATING-POINT HANDLERS -- IT WOULD COME OUT TO 20 UNLESS THEY HAD ROUNDING ERRORS.

